Perforce Software, Inc. 510.864.7400 consulting@perforce.com www.perforce.com

Disaster Recovery Failover Plan Unix Replica Server

Table of Contents

1	Ove	rview	1
2	Faile	over Procedure	1
	2.1	Check replica status	1
	2.2	Stop access to master server – done on master server	1
	2.3	Check replica status	1
	2.4	Change the replica to become the master	1
	2.5	Update the crontab (Run all commands as perforce user)	2
	2.6	Change the original master to become the replica	2

1 Overview

The replica servers are being replicated using the Perforce built in server to server replication via the "p4 pull" command and a rsync script to replicate checkpoints. This document provides the steps to failover from the main server to a replica server.

2 Failover Procedure

2.1 Check replica status

This is just a verification that replication is up to date before we start the whole process.

On the replica machine, run p4 pull -lj to check the status of the replication. The command should return two matching journal sequence numbers.

2.2 Stop access to master server – done on master server

Change the protect table to block access from everyone except the admin user and the service user. To do that, make the last three lines of the protect take look like this:

```
list user * * -//...
super user service * * //...
super user perforce * * //...
```

2.3 Check replica status

On the replica machine by running p4 pull -lj to check the status of the replication. You want to wait for the replica to fully catch up before shutting down the master and replica instances. Once you have verified the replication is up to date:

stop the replica by running /p4/1/bin/p4d_1_init stop on the replica server stop the master by running /p4/1/bin/p4d_1_init stop on the master server

2.4 Change the replica to become the master

Change the DNS entry for the machine you are failing over to point to the new master server.

On the replica server, edit /p4/<INSTANCE>/root/server.id and change the name to:

master

and save the file. Now you can restart the server as the master by running /p4/1/bin/p4d 1 init start.

Edit the protect table and remove the list user * * -//... line that was added in the earlier step.

After this is done, the former replica is now the master.

Next run:

```
rm /p4/1/root/state
rm /p4/1/root/rdb.lbr
```

2.5 Update the crontab (Run all commands as perforce user)

On the new master server, originally the replica, run crontab /p4/p4.crontab to reset the crontab to run the master server crontab settings.

On the original master server, now the replica, run crontab /p4/p4.crontab.replica to change it to run the replica scripts.

It is a good idea to use crontab -1 > p4.crontab on the master and crontab -1 > p4.crontab.replica on the replica before you make these changes on each machine just to be sure that you have the current crontab settings saved. You can copy these files to the other machine to make sure you load the current settings on the other machine as well.

2.6 Change the original master to become the replica

On the original master, edit /p4/1/root/server.id and change the name to:

```
replica
```

and save the file.

Move /p4/1/logs/journal, e.g. to /p4/1/logs/journal.orig.master Delete the following files if they exist: /p4/1/root/state and /p4/1/root/rdb.lbr . You also need to login into the master server as the service user on the replica so that replication can run.

Run

```
/p4/common/bin/p4master_run 1 p4 -p ssl:master_dns_name:1666 login <
/p4/common/config/.p4passwd.p4_1.admin
/p4/common/bin/p4master run <instance> p4 -p ssl:master:port login service
```

Now, start the server as a replica by running /p4/1/bin/p4d 1 init start

Check replication by running:

```
p4 login < /p4/common/config/.p4passwd.p4_1.admin
p4 pull -lj</pre>
```

You should see two matching journal sequence numbers. The p4 pull -lj will only succeed when run on a replica pulling from a master. So this proves that the roles have been switched.

Finally, run these final two steps:

On the new replica server, run the sync_replica.sh command that cron normally runs in order to make sure it is working properly.

```
/p4/common/bin/p4master run 1 /p4/common/bin/sync replica.sh
```

NOTE 1: If the master server has been down for more than 7 days, you will have to reset the replica as follows before starting it. The reason for the 7 days value is that the number of old checkpoints and journals to keep is set to 7 in the p4_vars file. The replication uses the old journals in order to catch up from where it last stopped, so if the old ones have rotated off, you have to reset the replica with a new checkpoint and updated versioned files

To reset the replica, from the replica run:

Since your servers are set up to rsync without a password, you can reset the replica by running:

Make note of the highest numbered p4_1.ckp.#.gz file in that directory. Assume it is 10 for this example:

Optionally, you may want to run:

```
rsync -avz --delete perforce@master_server:/p4/1/depots/ /p4/1/depots
```

or

```
/p4/common/bin/p4master_run 1 /p4/common/bin/p4verify.sh
```

to make sure the depot files are up to date.

NOTE 2: If the master server is inoperable, follow these steps:

- (1) On the replica server, run /p4/1/bin/p4d 1 init stop
- (2) Do the steps in Section 2.4 above